

LogisticaTRUCKServer-Ⅲ距離運賃計算API .NETDLLの利用例

LogisticaTRUCKServer-Ⅲ距離運賃計算API .NET DLL VisualBaisc 利用例

サンプルプログラム

```
Imports Microsoft.VisualBasic
```

```
Public Class Form1
```

```
Private TRKSVR As lgsTrkSvr3NETX01.lgsTrkSvr3NETX01 ← 距離運賃計算サーバ・DOT.NETDLL lgsTrkSvr3NETX01.の参照
```

```
Private Sub 距離運賃計算ToolStripMenuItem_Click(ByVal sender As System.Object, ByVal e As System.EventArgs) Handles 距離運賃計算ToolStripMenuItem.Click
```

```
Dim blnCond As Boolean
```

```
blnCond = TRKSVR.ServerConnect
```

```
If blnCond = True Then
```

```
TRKSVR.SanshouKyorikeisan = Me.TextBox参照距離計算.Text
```

```
TRKSVR.Hatsuten = Me.TextBox発点.Text
```

```
TRKSVR.Chakuten = Me.TextBox着点.Text
```

```
TRKSVR.HatsutenBangou = Me.TextBox発点割付番号.Text
```

```
TRKSVR.UnchinTaikaiBangou = Me.TextBox運賃体系割付番号.Text
```

```
TRKSVR.ServiceBangou = Me.TextBoxサービス割付番号.Text
```

```
TRKSVR.ZougenRitsu = Me.TextBox増減率.Text
```

```
TRKSVR.Kagen = Me.TextBox加減.Text
```

```
TRKSVR.HasuuTani = Me.TextBox端数単位.Text
```

```
TRKSVR.HasuuShori = Me.TextBox端数処理.Text
```

```
If IsNumeric(Me.TextBox最大積載量Kg.Text) = True Then
```

```
TRKSVR.SaidaiSekisaiRyouKg = Me.TextBox最大積載量Kg.Text
```

```
End If
```

```
TRKSVR.JuuryouKg = Me.TextBox重量.Text
```

```
TRKSVR.NiSuu = Me.TextBox個数.Text
```

```
TRKSVR.KyoriKensakuHouhou = Me.TextBox距離検索方法.Text
```

```
If Me.TextBox距離検索方法.Text = "3" Then
```

```
TRKSVR.KyoriKm = Me.TextBox距離Km.Text
```

```
End If
```

```
TRKSVR.UnsouHizuke = Me.TextBox運送日付.Text
```

```
blnCond = TRKSVR.Keisan ← 距離運賃計算依頼
```

```
If blnCond = True Then
```

```
Me.TextBox 距離 Km.Text = TRKSVR.KyoriKm ← 距離運賃計算結果
```

```
Me.TextBox距離Km.Text = TRKSVR.KyoriKm
```

```
Me.TextBox合計運賃.Text = TRKSVR.GoukeiUnchin
```

```
Me.TextBox基本運賃.Text = TRKSVR.KihonUnchin
```

```
Me.TextBox付加運賃.Text = TRKSVR.FukaUnchin
```

```
Me.TextBox運送保険料.Text = TRKSVR.FukaHokenRyou
```

```
Me.TextBox諸料金.Text = TRKSVR.FukaShoRyoukin
```

```
Me.TextBox航送料.Text = TRKSVR.FukaKousouRyou
```

```
Me.TextBox集荷配達料.Text = TRKSVR.FukaShuukaHaisouRyou
```

```
Me.TextBox冬期割増料.Text = TRKSVR.FukaToukiWariMashiRyou
```

```
Me.TextBox地区割増料.Text = TRKSVR.FukaChikuWariMashiRyou
```

```
Me.TextBox連絡運輸中継料.Text = TRKSVR.FukaUnyuChuukeiRyou
```

```
Me.TextBoxエラー状況.Text = TRKSVR.ErrorJoukyou
```

```
Else
```

```
Me.TextBoxエラー状況.Text = TRKSVR.ErrorJoukyou
```


```

End If
End Sub
Private Sub Form1_FormClosed(ByVal sender As Object, ByVal e As System.Windows.Forms.FormClosedEventArgs) Handles Me.FormClosed
    End
End Sub
Private Sub Form1_Load(ByVal sender As Object, ByVal e As System.EventArgs) Handles Me.Load
    Me.TextBox参照距離計算.Text = 2
    Me.TextBox距離検索方法.Text = "1"
    Me.TextBox発点.Text = "新潟県三条市"
    Me.TextBox着点.Text = "佐賀県鳥栖市"
    Me.TextBox運賃体系割付番号.Text = 1
    Me.TextBoxサービス割付番号.Text = 1
    Me.TextBox発点割付番号.Text = 1
    Me.TextBox増減率.Text = "0.00"
    Me.TextBox加減.Text = "+"
    Me.TextBox端数処理.Text = 1
    Me.TextBox端数単位.Text = 100
    Me.TextBox重量.Text = 120
    Me.TextBox個数.Text = 2
    Me.TextBox距離Km.Text = 0
    Me.TextBox合計運賃.Text = 0
    Me.TextBoxエラー状況.Text = ""
    'サーバ接続

    TRKSVR = New IgsTrkSvr3NETX01.IgsTrkSvr3NETX01 ← 距離運賃計算サーバ DOT.NETDLL IgsTrkSvr3NETX01.の定義
    TRKSVR.IpAdress = "Mdv4420stn" ← 距離運賃DBサーバが稼働するコンピュータ名、IPアドレスを指定する
End Sub
End Class

```

実行画面



導入以前に、動作確認・評価試用のための評価試用版 CD の無料貸し出しがあります。